

SET Geodelivery secured access

Login procedure

AIRBUS

Page n°i2

Abbreviations and acronyms

ADSI	Airbus Defence and Space - Intelligence
FTP	File Transfer Protocol
FTPs	File Transfer Protocol Secure
sFTP	SSH File Transfer Protocol
SSH	Secure Shell
SET	Service d'Echange et de Transfert (File Exchange Service)



Page n°i3

Contents

1 Introduction	n1	l
2 Connection	n to Geodelivery)
2.1 Usina V	Web Portal	>
2.2 Using F	FTP	>
2.2.1 All	lowed protocols	>
2.2.2 Ex	xample with FileZilla	>
2.2.3 Ex	xample with lftp	5
2.3 Trouble	eshooting	5
2.3.1 Ac	ctivate debug mode with lftp	5
2.3.2 Ac	ctivate debug mode in FileZilla6	3



AIRBUS

1 Introduction

Geodelivery is the Airbus DS GEO product delivery service.

All products can be downloaded from Geodelivery through FTP connection or through web portal. This procedure describe how to connect to Geodelivery.

Page n°2

2 Connection to Geodelivery

2.1 Using Web Portal

Geodelivery provides a web portal access through the URL <u>https://geodelivery.intelligence-airbusds.com/login.html</u> Open the URL, the login page asks you to enter the credentials given by your customer support.

Compte:			Se souvenir de moi
Mot de passe:			
Langue:	Français	~	Connexion

Note: before sending your credential, please check that the certificate is valid (for instance with Google Chrome geodelivery.intelligence-airbusds.com/login.html
). This ensure that your personal credential will not be intercepted.

Once connected, you will see all shared products and data. You can download data and (according to the write access on your account) push data to the server.

2.2 Using FTP

2.2.1 Allowed protocols

According to your project's settings, you can connect to Geodelivery using secured FTP dataflow:

Protocol	Host	Login	Command port	Data port
FTP	No	ot allowed after 25 th January 2	2022	
sFTP (ssh)			2200	
FTPs implicit	geodelivery.intelligence-airbusds.com	Given by your customer contact	990	40000-50000
FTPS explicit			21	40000-50000

2.2.2 Example with FileZilla

Please activate sending keep alive commands:



- Open the "settings" section :
- In the FTP section, check the "send FTP keep-alive commands" box :

Settings	
Select page:	Overview
Connection	For more detailed information about what these options do, please run the network configuration wizard. Run configuration wizard now
FTP Proxy	Transfer Mode
- SFTP	Passive (recommended)
- Transfers	◯ Active
- FTP: File Types	Allow fall back to other transfer mode on failure
File exists action	If you have problems to retrieve directory listings or to transfer files, try to change the default transfer mode.
- Passwords	FTP Koop alive
- Date/time format	Send FTP keep-alive commands
- Filesize format	A proper server does not require this. Contact the server administrator if you need this.
Language	



Geodelivery secured access - Login procedure

Page n°3

Note for Airbus DS GEO users only:

From Airbus DS GEO network, you have to bypass the proxy is your FTP connection advanced properties

General	Advanced		Transfer Settings Charset		
Server type: Defau		Defau	It (Autodetect)		\sim
Bypass proxy					

2.2.2.1 Using sFTP

General Adv	anced Transfer Settings Charset		
Protocol:	Protocol: SFTP - SSH File Transfer Protocol		
Host:	geodelivery.intelligence-airbusds.com Port: 2200		
Logon Type:	Normal		
Logon type.	on type. Normal V		
User:			
Password:	k internet in the second se		

2.2.2.2 Using FTPs in explicit mode

General	Adva	anced Transfer Settings Charset				
Protoco	Protocol: FTP - File Transfer Protocol ~					
Host:		geod	geodelivery.intelligence-airbusds.com Port:			
Encrypti	on:	Requi	Require explicit FTP over TLS ~			
Logon T	ype:	Normal				
User:						
Passwor	d:					

Accept the certificate

Subject

7	alect	
	Common name:	geodelivery.intelligence-airbusds.com
	Organization:	Airbus DS Geo SA
	Country:	FR
	State or province:	HAUTE-GARONNE
	Locality:	TOULOUSE
	Alternative names:	geodelivery.intelligence-airbusds.com geodelivery.astrium-geo.com geodelivery.spotimage.fr

Tip: check the two last check box to allow Geodelivery's certificate without asking again

Trust the server certificate and carry on connecting?

Always trust this certificate in future sessions.

Trust this certificate on the listed alternative hostnames.

Page n°4

2.2.2.3 Using FTPs in implicit mode

General	Adva	nced	Transfer Settings	Charset		
Protocol: FTP - File Transfer Protocol		\sim				
Host:	Host: geodelivery.intelligence-airbusds.com Port: 990					
Encryption: Requi		Requi	uire implicit FTP over TLS			\sim
Logon Type: Normal		\sim				
User:	[100000				
Password	d: [

Accept the certificate if the common name is:

Subject

bject	
Common name:	geodelivery.intelligence-airbusds.com
Organization:	Airbus DS Geo SA
Country:	FR
State or province:	HAUTE-GARONNE
Locality:	TOULOUSE
Alternative names:	geodelivery.intelligence-airbusds.com geodelivery.astrium-geo.com geodelivery.spotimage.fr
	Common name: Organization: Country: State or province: Locality: Alternative names:

Tip: check the two last check box to allow Geodelivery's certificate without asking again

Trust the server certificate and carry on connecting?

Always trust this certificate in future sessions.

Trust this certificate on the listed alternative hostnames.

2.2.3 Example with Iftp

2.2.3.1 sFTP

USER="GivenByYourCustomerContact"
PASSWORD="GivenByYourCustomerContact"
lftp sftp://\$USER:\$PASSWORD@geodelivery.intelligence-airbusds.com:2200 -e "debug;set sftp:connect-program ssh -a -x
-c aes128-cbc -o KexAlgorithms=diffie-hellman-group1-sha1;ls;quit;"

Remark: on the first connection, the rsa host fingerprint is unknown. If a Host key verification failed occurs, add the Geodelivery fingerprint in your trusted store with

ssh -p 2200 geodelivery.intelligence-airbusds.com -oKexAlgorithms=+diffie-hellman-group1-sha1 -c aes128-cbc

2.2.3.2 FTPs implicit

```
USER="GivenByYourCustomerContact"
PASSWORD="GivenByYourCustomerContact"
lftp ftps://$USER:$PASSWORD@geodelivery.intelligence-airbusds.com:990 -e "ls;quit;"
```

2.2.3.3 FTPS explicit

```
USER="GivenByYourCustomerContact"
PASSWORD="GivenByYourCustomerContact"
lftp ftps://$USER:$PASSWORD@geodelivery.intelligence-airbusds.com -e "ls;quit;"
```

2.3 Troubleshooting

If you have any issue while connecting to Geodelivery, please contact customer support team:

- Write an email to your customer care contact or intelligence-customer_support@airbus.com
- Give as many information as possible :
 - o What is the project affected by the trouble, which account(s) is(are) affected
 - Is it your first connection or was the data flow previously working ?
 - What is your outgoing IP address (go to https://www.whatismyip.com/ for instance to get your IP)
 - At what time did the error occur?
 - What is the complete error message? Please feel free to add screen shots to your issue report in order to let us make a deep analysis of the issue

In order to help the Geodelivery team, please use debug mode. This will add lots of details on your issue context:

2.3.1 Activate debug mode with Iftp

Before sending any command with lftp, please enter the command "debug".

For instance : date '+%Y-%m-%d-%H-%m-%S' lftp -p 2200 ftp://\$USER:\$PASSWORD@geodelivery.intelligence-airbusds.com -e "debug;ls;quit;"

The output with debug option will add many useful details, for instance the connection step, the certificate exchange and validation, and the date send just before your lftp command will make it possible to correlate your issue to FTP server's log.

2.3.2 Activate debug mode in FileZilla

Please open the FileZilla settings



In the Logging section, check the following : "show timestamps in message log"

Settings		
Select page: 	~	Logging Show timestamps in message log Log to file Filename: Limit size of logfile Limit: 10 MiB If the size of the logfile reaches the lin to the end of the filename (possibly o new file gets created. Changing logfile settings requires restart o

In the Debug section, choose the "debug" level

Reference:S-PO-CA6-02-ADSIIssue:1SETRevision:0Geodelivery secured access - LoginDate:11/01/2022procedure



Page n°AN1

END OF DOCUMENT